
HiTechnic Sensor Multiplexer Programmer's Guide



Version 1.0.1

November 25, 2009

By Xander Soldaat



Contents

The HiTechnic Sensor Multiplexer	3
Introduction	3
Operational states	3
Multiplexer Operation	3
How does it do what it does?	3
Programming examples	4
Putting it all together	6
Advanced operations	9
Dealing with the unexpected	11
3 rd Party ROBOTC Driver Suite	12
Appendix A Register Layout + Function	13
Appendix B: SMUX Status	14
Appendix C: Channel Mode	15
Appendix D: Channel Type	15
Appendix F: Supported sensors	15

Thanks to John Hansen for reviewing the NXC code and John, Steve and Gus from HiTechnic for reviewing this document and providing me with all the necessary information.

The HiTechnic Sensor Multiplexer

Introduction



The HiTechnic Sensor Multiplexer (SMUX) allows you to read up to 4 supported analogue or digital sensors via a single NXT sensor port.

The SMUX itself is a digital sensor that can be configured and queried through I2C. To use the SMUX in programming environments such as ROBOTC or NXC, it's necessary to have a basic understanding of its operation.

Operational states

The SMUX has 3 basic operational states; **halted**, **autodetect** and **running**.



The **halted** state has to be entered before any other command is given to the SMUX.

When the **autodetect** state is entered, the SMUX will attempt to probe the sensors currently attached to its ports.



Running

If the sensor is a digital one, the information returned to the SMUX is compared to an internal lookup table. If the sensor is found in this table, it populates the internal configuration registers (See: Appendix A) with the information required to read that sensor. If the sensor is not found or doesn't respond to I2C queries, that SMUX port is configured as analogue. The list of supported sensors can be found in Appendix E. The SMUX takes approximately 500ms to complete the scan. Care should be taken not to issue any new commands during this cycle. The autodetect state may only be entered when the SMUX is in a halted state. When the autodetect state exits, the SMUX will automatically revert to the halted state.

To start reading the sensors connected to the SMUX, it must enter the **running** state. This state may only be entered from the **halted** state.

Multiplexer Operation

How does it do what it does?

The SMUX works by querying the connected sensors on behalf of the user. The results from these queries are stored in the registers 40-4FH, 50-5FH, 60H-6FH, 70-7FH for sensors 1, 2, 3 and 4 respectively. In the case of an analogue sensor, the 10 bit values can be retrieved from registers 36-37H, 38-39H, 3A-3BH and 3C-3DH for analogue sensors 1, 2, 3 and 4 respectively. So how does the SMUX know what to ask for? Parameters such as the sensor's I2C address, the number of bytes to ask for and the register to be queried are all stored in their respective registers as specified in Appendix A.

Depending on the type of sensor and the number of bytes that are queried, the SMUX may poll the sensor at different frequencies. Below is a table of the polling frequencies.

Sensor Type	I2C Byte Count	Polling Frequency		
Analogue	-	300Hz (roughly every 3ms)		
I2C	>= 8 50Hz (every 20ms)			
I2C	< 8	100Hz (every 10ms)		

Programming examples

Since theory is nothing without practice, here are some examples of how to use this SMUX using both NXC and ROBOTC.

```
Halting the SMUX
ROBOTC
                                                 NXC
void HTSMUXhalt(tSensors smux) {
                                                 void HTSMUXhalt (const byte smux) {
 ubyte sendMsg[4];
                                                   byte sendMsg[3];
  sendMsg[0] = 3;
                                                   sendMsg[0] = 0x10;
                                                                        // Address of SMUX
                     // size of I2C message
  sendMsg[1] = 0x10; // Address of SMUX
                                                   sendMsg[1] = 0x20; // Command register
  sendMsg[2] = 0x20; // Command register
                                                   sendMsq[2] = 0;
                                                                        // Command to be sent
  sendMsg[3] = 0;
                     // Command to be sent
                                                                        // (halt)
                     // (halt)
                                                   // Send the command to the SMUX to put it
  // Send the command to the SMUX to put it
                                                   // in halted state
  // in halted state
                                                   I2CWrite(smux, 0, sendMsg);
  sendI2CMsg(smux, sendMsg, 0);
                                                   // Wait 50ms after SMUX is halted
  // wait 50ms for the SMUX to clean up
                                                   Wait(50);
  Wait1Msec(50);
```

```
Initiating autodetect state
ROBOTC
                                                     NXC
void HTSMUXautodetect(tSensors smux)
                                                      void HTSMUXautodetect (const byte smux) {
  ubyte sendMsg[4];
                                                       byte sendMsg[3];
                                                        sendMsg[0] = 0x10; // Address of SMUX
                       // size of I2C message
  sendMsq[0] = 3;
  sendMsg[1] = 3; // size of 12C mess sendMsg[1] = 0 \times 10; // Address of SMUX
                                                        sendMsg[1] = 0x20;
                                                                              // Command register
  sendMsg[2] = 0x20; // Command register
                                                                              // Command to be sent
                                                        sendMsg[2] = 1;
                       // Command to be sent
                                                                              // (autodetect)
  sendMsg[3] = 1;
                       // (autodetect)
                                                        \ensuremath{//} Send the command to the SMUX to put it
  // Send the command to the SMUX to
                                                        // in halted state
  // start probing sensors.
                                                        I2CWrite(smux, 0, sendMsg);
  sendI2CMsg(smux, sendMsg, 0);
                                                        // Wait 500ms for autodetect to complete
  // Wait 500ms for autodetect to complete
                                                       Wait (500);
  wait1Msec(500);
```

```
Start normal multiplexer operation
ROBOTC
                                                 NXC
void HTSMUXrun (tSensors smux) {
                                                 void HTSMUXrun (byte smux) {
 ubyte sendMsq[4];
                                                   byte sendMsq[3];
 sendMsg[0] = 0x10;  // Address of SMUX
sendMsg[1] = 0x20;  // Command register
  sendMsg[2] = 0x20; // Command register
                                                   sendMsg[2] = 2;
                                                                       // Command to be sent
  sendMsg[3] = 2;
                   // Command to be sent
                                                                        // (run)
                     // (run)
                                                   // Send the command to the SMUX to put it
  // Send the command to the SMUX to put it
                                                   // in running state
  // in running state
                                                   I2CWrite(smux, 0, sendMsg);
  sendI2CMsg(smux, sendMsg, 0);
```

We can optimize the three functions into one with the following code

Sending a command to the SMUX				
ROBOTC	NXC			
#define HTSMUX_CMD_HALT 0x00 #define HTSMUX_CMD_AUTODETECT 0x01 #define HTSMUX_CMD_RUN 0x02	#define HTSMUX_CMD_HALT 0x00 #define HTSMUX_CMD_AUTODETECT 0x01 #define HTSMUX_CMD_RUN 0x02			
<pre>void HTSMUXsendCmd(tSensors smux, byte cmd) { ubyte sendMsg[4];</pre>	<pre>void HTSMUXsendCmd(byte smux, byte cmd) { byte sendMsg[3];</pre>			
<pre>sendMsg[0] = 3;</pre>	<pre>sendMsg[0] = 0x10; // Address of SMUX sendMsg[1] = 0x20; // Command register sendMsg[2] = cmd; // Command to be sent</pre>			
<pre>// Send the command to the SMUX sendI2CMsg(smux, sendMsg, 0);</pre>	<pre>// Send the command to the SMUX I2CWrite(smux, 0, sendMsg);</pre>			
<pre>// if the HTSMUX_CMD_AUTODETECT command has // been given, wait 500 ms if (cmd == HTSMUX_CMD_AUTODETECT) { wait1Msec(500);</pre>	<pre>// if the HTSMUX_CMD_AUTODETECT command has // been given, wait 500 ms if (cmd == HTSMUX_CMD_AUTODETECT) { Wait(500); // Wait 50ms after SMUX is halted</pre>			
<pre>// Wait 50ms after SMUX is halted } else if (cmd == HTSMUX_CMD_HALT) { wait1Msec(50); } </pre>	<pre>// Wait Sums after SMUX is naited } else if (cmd == HTSMUX_CMD_HALT) { Wait(50); } }</pre>			

Now that we know how to get the SMUX into the three states, **halted**, **autodetect** and **running**, let's see about making it work for us.

If you look at <u>Appendix A</u>, you'll see that registers 40-4FH, 50-5FH, 60-6FH and 70-7FH, the I2C buffers, are all 16 bytes wide. This is no coincidence, it is the maximum size read reply the NXT can handle. Each time the SMUX polls a sensor, the data returned from it is placed in its respective I2C buffer.

```
Reading polled data from an I2C sensor
ROBOTC
                                              NXC
typedef struct
                                              bool HTSMUXreadI2C (byte smux, byte chan,
 ubyte arr[16];
                                                                 byte offset, byte length,
} byte array;
                                                                 byte &data[]) {
void HTSMUXreadI2C (tSensors smux, byte chan,
                                                byte sendMsq[2];
                 byte offset, byte length,
                                                sendMsg[0] = 0x10;
                                                                     // Address of SMUX
                  byte_array &array) {
                                                                     // Buffer register
                                                sendMsg[1] = 0x40 + (chan * 16) + offset;
 ubyte sendMsg[3];
 // Query the SMUX and read the response
                                                return I2CBytes(smux, sendMsg, length, data);
                      // Buffer register
 sendMsg[2] = 0x40 + (chan * 16) + offset;
 // Query the SMUX and read the response
 sendI2CMsg(smux, sendMsg, length);
 wait1Msec(10);
 readI2CReply(smux, array.arr[0], length);
```

If the sensor is an analogue one, you have to query different buffers. Judging by Appendix A, the registers we're going to want to read are 36-37H, 38-39H, 3A-3BH and 3C-3DH, 2 bytes for each channel. The SMUX's analogue data is 10 bits wide, the same as the native NXT bit width. The first byte contains the upper 8 bits and the second byte contains the lower 2 bits.

Reading polled data from an analogue sensor	
ROBOTC	NXC
int HTSMUXreadAD (tSensors smux, byte chan) {	int HTSMUXreadAD (byte smux, byte chan) {
<pre>ubyte sendMsg[3]; ubyte readMsg[2]; sendMsg[0] = 2;</pre>	<pre>byte sendMsg[2]; byte readMsg[2]; const byte count = 2; sendMsg[0] = 0x10;</pre>
<pre>// Query the SMUX and read the response sendI2CMsg(smux, sendMsg, 2); wait1Msec(10); readI2CReply(smux, readMsg, 2); // ensure no weirdness from signed/unsigned // conversions return (readMsg[0] & 0x00FF) * 4 +</pre>	<pre>// Query the SMUX and read the response if (I2CBytes(smux, sendMsg, count, readMsg)) // ensure no weirdness from signed/unsigned // conversions return (readMsg[0] & 0x00FF) * 4 +</pre>

Putting it all together

Now that we know how to work the basics of the SMUX, it's time to put it all together. I've used a HiTechnic Colour Sensor V2 and a Gyro in my tests; you can use whatever you'd like, as long as it's supported by the SMUX. You may need to modify the program to properly reassemble the data from the sensors in question.

```
Reading a HiTechnic colour sensor (I2C) attached to port 1 of a SMUX
ROBOTC
                                                    NXC
#define HTSMUX CMD HALT
                                 0×00
                                                    #define HTSMUX CMD HALT
                                                                                      0.0 \times 0.0
#define HTSMUX CMD AUTODETECT
                                 0 \times 01
                                                    #define HTSMUX CMD AUTODETECT
                                                                                      0 \times 01
#define HTSMUX CMD RUN
                                 0 \times 02
                                                    #define HTSMUX CMD RUN
                                                                                      0 \times 02
typedef struct {
                                                    void HTSMUXsendCmd(byte smux, byte cmd) {
 ubyte arr[16];
                                                      byte sendMsg[3];
} byte_array;
                                                      sendMsg[0] = 0x10;
                                                                            // Address of SMUX
                                                                            // Command register
void HTSMUXsendCmd(tSensors smux, byte cmd) {
                                                      sendMsg[1] = 0x20;
                                                                            \ensuremath{//} Command to be sent
 ubyte sendMsg[4];
                                                      sendMsg[2] = cmd;
  sendMsg[0] = 3;
                         // size of I2C message
                                                      // Send the command to the SMUX
  sendMsg[1] = 0x10;
                        // Address of SMUX
                                                      I2CWrite(smux, 0, sendMsg);
  sendMsq[2] = 0x20;
                        // Command register
  sendMsg[3] = cmd;
                        // Command to be sent
                                                      // if the HTSMUX CMD AUTODETECT command has
                                                      // been given, wait 500 \text{ ms}
  // Send the command to the SMUX
                                                      if (cmd == HTSMUX CMD AUTODETECT) {
  sendI2CMsg(smux, sendMsg, 0);
                                                        Wait(500);
  // if the HTSMUX CMD AUTODETECT command has
                                                      // Wait 50ms after SMUX is halted
  // been given, wait \overline{500} ms
                                                      } else if (cmd == HTSMUX CMD HALT) {
  if (cmd == HTSMUX CMD AUTODETECT) {
                                                        Wait(50);
    wait1Msec(500);
                                                    }
  // Wait 50ms after SMUX is halted
  } else if (cmd == HTSMUX CMD_HALT) {
                                                    bool HTSMUXreadI2C (byte smux, byte chan,
    wait1Msec(50);
                                                                          byte offset, byte length,
                                                                          byte &data[]) {
                                                      byte sendMsq[2];
void HTSMUXreadI2C (tSensors smux, byte chan,
                      byte offset, byte length,
                                                      sendMsg[0] = 0x10;
                                                                             // Address of SMUX
                                                                             // Buffer register
                     byte array &array) {
                                                      sendMsg[1] = 0x40 + (chan * 16) + offset;
 ubyte sendMsg[3];
                                                      // Query the SMUX and read the response
 sendMsq[0] = 2;
                         // size of I2C message
                                                      return I2CBytes(smux, sendMsg, length, data);
  sendMsg[1] = 0x10;
                         // Address of SMUX
                         // Buffer register
  sendMsg[2] = 0x40 + (chan * 16) + offset;
                                                    task main () {
                                                      byte data[16];
  \ensuremath{//} Query the SMUX and read the response
                                                      SetSensorLowspeed(S1);
  sendI2CMsg(smux, sendMsg, length);
                                                      Wait(100);
 wait1Msec(10):
 readI2CReply(smux, array.arr[0], length);
                                                      // first send the halt command to the SMUX
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD HALT);
                                                      // Initiate scan
task main () {
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD AUTODETECT);
                                                      // Start normal operation
 byte_array data;
  SetSensorType(S1, sensorLowSpeed);
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD RUN);
 wait1Msec(100);
                                                      while (true) {
  // first send the halt command to the SMUX
                                                         // Read a single byte from the I2C
 HTSMUXsendCmd(S1, HTSMUX_CMD_HALT);
                                                         // buffer for channel 0 (SMUX port 1)
                                                         HTSMUXreadI2C(IN 1, 0, 0, 1, data);
  // Initiate scan
 HTSMUXsendCmd(S1, HTSMUX CMD AUTODETECT);
                                                         NumOut(0, LCD LINE2, data[0], true);
  // Start normal operation
                                                         Wait(100);
 HTSMUXsendCmd(S1, HTSMUX CMD RUN);
                                                      }
                                                    }
 while (true) {
     // Read a single byte from the I2C
     // buffer for channel 0 (SMUX port 1)
     HTSMUXreadI2C(S1, 0, 0, 1, data);
     nxtDisplayTextLine(2, "%d", data.arr[0]);
     wait1Msec(100);
```

```
Reading a HiTechnic Gyro sensor (analogue) attached to port 1 of a SMUX
ROBOTC
                                                    NXC
#define HTSMUX_CMD_HALT
                                 0×00
                                                    #define HTSMUX CMD HALT
                                                                                     0 \times 00
#define HTSMUX CMD AUTODETECT
                                 0 \times 01
                                                    #define HTSMUX CMD AUTODETECT
                                                                                     0 \times 01
#define HTSMUX CMD RUN
                                 0 \times 02
                                                    #define HTSMUX CMD RUN
                                                                                     0 \times 02
void HTSMUXsendCmd(tSensors smux, byte cmd) {
                                                    void HTSMUXsendCmd(byte smux, byte cmd)
 ubyte sendMsg[4];
                                                      byte sendMsg[3];
  sendMsg[0] = 3;
                        // size of I2C message
                                                      sendMsg[0] = 0x10;
                                                                            // Address of SMUX
 sendMsg[1] = 0x10;
                        // Address of SMUX
                                                                           // Command register
                                                      sendMsg[1] = 0x20;
                                                                           \ensuremath{//} Command to be sent
  sendMsg[2] = 0x20;
                        // Command register
                                                      sendMsg[2] = cmd;
  sendMsq[3] = cmd;
                        // Command to be sent
                                                      // Send the command to the SMUX
  // Send the command to the SMUX
                                                      I2CWrite(smux, 0, sendMsg);
  sendI2CMsq(smux, sendMsq, 0);
                                                      // if the HTSMUX CMD AUTODETECT command has
  // if the HTSMUX CMD AUTODETECT command has
                                                      // been given, wait 500 \text{ ms}
  // been given, wait 500 ms
                                                      if (cmd == HTSMUX CMD AUTODETECT) {
  if (cmd == HTSMUX CMD AUTODETECT) {
                                                        Wait(500);
    wait1Msec(500);
                                                      // Wait 50ms after SMUX is halted
                                                      } else if (cmd == HTSMUX CMD HALT) {
  // Wait 50ms after SMUX is halted
  } else if (cmd == HTSMUX_CMD_HALT) {
                                                        Wait(50);
    wait1Msec(50);
                                                    }
}
                                                    int HTSMUXreadAD (byte smux, byte chan) {
int HTSMUXreadAD (tSensors smux, byte chan) {
                                                      byte sendMsq[2];
  ubyte sendMsg[3];
                                                      byte readMsg[2];
 ubyte readMsg[2];
                                                      const byte count = 2;
  sendMsg[0] = 2;
                        // size of I2C message
                                                      sendMsg[0] = 0x10;
                                                                             // Address of SMUX
                        // Address of SMUX
                                                                             // Buffer register
  sendMsg[1] = 0x10;
                         // Buffer register
                                                      sendMsg[1] = 0x36 + (chan * 2);
  sendMsg[2] = 0x36 + (chan * 2);
                                                      // Query the SMUX and read the response
  // Query the SMUX and read the response
                                                      if (I2CBytes(smux, sendMsg, count, readMsg))
  sendI2CMsg(smux, sendMsg, 2);
                                                        // ensure no weirdness from signed/unsigned
  wait1Msec(10);
                                                        // conversions
  readI2CReply(smux, readMsg, 2);
                                                        return (readMsg[0] & 0x00FF) * 4 +
                                                               (readMsg[1] & 0x00FF);
  // ensure no weirdness from signed/unsigned
                                                      else
  // conversions
                                                        return 0;
 return (readMsg[0] & 0x00FF) * 4 +
         (readMsg[1] & 0x00FF);
                                                    task main () {
                                                      int data = 0;
task main () {
                                                      SetSensorLowspeed(S1);
 int data = 0;
                                                      Wait (100);
  SetSensorType(S1, sensorLowSpeed);
 wait1Msec(100);
                                                      // first send the halt command to the SMUX
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD HALT);
  // first send the halt command to the SMUX
                                                      // Initiate scan
 HTSMUXsendCmd(S1, HTSMUX_CMD_HALT);
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD AUTODETECT);
  // Initiate scan
                                                      // Start normal operation
 HTSMUXsendCmd(S1, HTSMUX CMD AUTODETECT);
                                                      HTSMUXsendCmd(IN_1, HTSMUX_CMD_RUN);
  // Start normal operation
                                                      Wait(50);
 HTSMUXsendCmd(S1, HTSMUX CMD RUN);
                                                      while (true) {
  wait1Msec(50);
                                                         // Read a single byte from the I2C
                                                         // buffer for channel 0 (SMUX port 1)
  while (true) {
     // Read a single byte from the AD
                                                         data = HTSMUXreadAD (IN 1, 0);
     // buffer for channel 0 (SMUX port 1)
                                                         NumOut(0, LCD LINE2, data, true);
     data = HTSMUXreadAD (S1, 0, 0, 1, data);
                                                         Wait(100);
     nxtDisplayTextLine(2, "%d", data);
                                                      }
     wait1Msec(100);
                                                    }
```

Advanced operations

So what to do if you are using the Lego Light sensor and you want to turn the light on or off? Well, it's not as tricky as you might think. You can use the channel mode registers, 22H, 27H, 2CH and 31H to enable or disable the digO pin for each individual SMUX channel. This is the pin used by the Light Sensor to check if it should enable or disable the LED. Incidentally, this is also the method for switching a sound sensor from dB to dBA mode and the HiTechnic EOPD sensor from Long Range to Short Range mode. For this example we'll use the Light Sensor, however.

Das blinkenlichten – switching the light on and off	
ROBOTC	NXC
#define HTSMUX_CHAN_NONE 0x00 #define HTSMUX_CHAN_DIGO_HIGH 0x04	#define HTSMUX_CHAN_NONE 0x00 #define HTSMUX_CHAN_DIGO_HIGH 0x04
<pre>void HTSMUXenableActive(tSensors smux,</pre>	void HTSMUXenableActive(byte smux, byte chan, bool active) {
ubyte sendMsg[4];	<pre>byte sendMsg[3];</pre>
<pre>sendMsg[0] = 3;</pre>	<pre>sendMsg[0] = 0x10; // Address of SMUX</pre>
<pre>if (active) sendMsg[3] = HTSMUX_CHAN_DIGO_HIGH; else sendMsg[3] = HTSMUX_CHAN_NONE;</pre>	<pre>sendMsg[2] = HTSMUX_CHAN_DIGO_HIGH; else sendMsg[2] = HTSMUX_CHAN_NONE; // Send the command to the SMUX</pre>
<pre>// Send the command to the SMUX sendI2CMsg(smux, sendMsg, 0); }</pre>	I2CWrite(smux, 0, sendMsg); }



When you call the HTSMUXenableActive() function, it is important that the SMUX is in a **halted** state. That means you must halt the SMUX using HTSMUXsendCmd(S1, HTSMUX_CMD_HALT), issue the HTSMUXenableActive() for the right channel and the tell the SMUX to resume polling by putting it back in the **running** state with HTSMUXsendCmd(S1, HTSMUX_CMD_RUN). That might seem awfully complicated but it's not that hard. Just always remember to **halt** the SMUX before modifying registers and put it back in a **running** state when you want to resume polling.

We can have a little fun with this function. Using four Light Sensors and a SMUX, you can make a Cylon "eye" by switching them on and off in a sequence.

You can watch a video of this in action here: http://www.youtube.com/watch?v=6IniYOOdBOc

```
By your command
ROBOTC
                                                    NXC
#define HTSMUX CHAN NONE
                                                     #define HTSMUX CHAN NONE
                                  0 \times 00
                                                                                      0 \times 00
#define HTSMUX CHAN DIGO HIGH
                                 0 \times 0.4
                                                     #define HTSMUX CHAN DIGO HIGH
#define HTSMUX CMD HALT
                                 0x00
                                                     #define HTSMUX CMD HALT
                                                                                      0x00
#define HTSMUX CMD AUTODETECT
                                                     #define HTSMUX CMD AUTODETECT
                                 0 \times 01
                                                                                      0 \times 01
#define HTSMUX CMD RUN
                                                    #define HTSMUX CMD RUN
                                 0x02
void HTSMUXsendCmd(tSensors smux, byte cmd) {
                                                    void HTSMUXsendCmd(byte smux, byte cmd) {
 ubyte sendMsg[4];
                                                      byte sendMsg[3];
                                                      sendMsg[0] = 0x10;  // Address of SMUX
sendMsg[1] = 0x20;  // Command register
 sendMsq[0] = 3;
                        // size of I2C message
                        // Address of SMUX
 sendMsg[1] = 0x10;
  sendMsg[2] = 0x20;
                        // Command register
                                                       sendMsg[2] = cmd;
                                                                            // Command to be sent
  sendMsq[3] = cmd;
                        // Command to be sent
                                                       // Send the command to the SMUX
 // Send the command to the SMUX
                                                      I2CWrite(smux, 0, sendMsg);
 sendI2CMsg(smux, sendMsg, 0);
                                                       // if the HTSMUX CMD AUTODETECT command has
                                                       // been given, wait \overline{500} ms
  // if the HTSMUX CMD AUTODETECT command has
  // been given, wait 500 \text{ ms}
                                                      if (cmd == HTSMUX CMD AUTODETECT) {
 if (cmd == HTSMUX_CMD_AUTODETECT) {
                                                        Wait(500);
    wait1Msec(500);
                                                       // Wait 50ms after SMUX is halted
  // Wait 50ms after SMUX is halted
                                                      } else if (cmd == HTSMUX CMD HALT) {
  } else if (cmd == HTSMUX CMD HALT) {
                                                        Wait(50);
    wait1Msec(50);
                                                    void HTSMUXenableActive(byte smux,
void HTSMUXenableActive(tSensors smux,
                                                                             byte chan,
                                                                             bool active) {
                        byte chan,
                         bool active) {
                                                      byte sendMsg[3];
 ubyte sendMsg[4];
                                                      sendMsg[0] = 0x10;
                                                                            // Address of SMUX
 sendMsg[0] = 3;

sendMsg[1] = 0x10;
                       // size of I2C message
                                                                             // Channel mode register
                      // Address of SMUX
                                                       sendMsg[1] = 0x22 + (chan * 5);
  sendMsg[2] = 0x22 + (chan * 5); // channel
                                    // mode reg
                                                      if (active)
 if (active)
                                                        sendMsg[2] = HTSMUX CHAN DIGO HIGH;
    sendMsg[3] = HTSMUX CHAN DIGO HIGH;
 else
                                                        sendMsg[2] = HTSMUX CHAN NONE;
   sendMsg[3] = HTSMUX CHAN NONE;
                                                       // Send the command to the SMUX
 // Send the command to the SMUX
                                                      I2CWrite(smux, 0, sendMsg);
 sendI2CMsg(smux, sendMsg, 0);
                                                    task main () {
task main () {
                                                      SetSensorLowspeed(S1);
 SetSensorType(S1, sensorLowSpeed);
                                                      Wait (100);
  wait1Msec (100);
                                                       // first send the halt command to the SMUX
  // first send the halt command to the SMUX
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD HALT);
 HTSMUXsendCmd(IN_1, HTSMUX_CMD_HALT);
                                                       // Initiate scan
  // Initiate scan
                                                      HTSMUXsendCmd(IN 1, HTSMUX CMD AUTODETECT);
 HTSMUXsendCmd(IN 1, HTSMUX CMD AUTODETECT);
                                                      while (true) {
                                                        for (int i = 0; i < 4; i++) {
 while (true) {
   for (int i = 0; i < 4; i++) {
                                                          HTSMUXenableActive(IN_1, i, true);
      HTSMUXenableActive(IN 1, i, true);
                                                           Wait (20);
                                                           HTSMUXsendCmd(IN 1, HTSMUX CMD RUN);
      Wait (20);
      HTSMUXsendCmd(IN 1, HTSMUX CMD RUN);
                                                           Wait(100);
                                                          HTSMUXsendCmd(IN 1, HTSMUX CMD HALT);
      Wait (100);
      HTSMUXsendCmd(IN 1, HTSMUX CMD HALT);
                                                          HTSMUXenableActive(IN 1, i, false);
      HTSMUXenableActive(IN 1, i, false);
                                                          Wait(10);
      Wait(10);
    }
                                                      }
                                                    }
  }
```

Dealing with the unexpected

As with all things in life, not everything goes according to plan. The SMUX is no exception. So how do you find out what's bugging the SMUX when you stop getting sane sensor data back from it? How do you check if the batteries powering the SMUX are still good enough? Have a look at the status register and the meaning of its bit fields in <u>Appendix B</u>. You can read this register without needing to be in a **halted** state.

Reading the SMUX status register	
ROBOTC	NXC
#define HTSMUX_STAT_NORMAL 0x00 #define HTSMUX_STAT_BATT 0x01 #define HTSMUX_STAT_BUSY 0x02 #define HTSMUX_STAT_HALT 0x04 #define HTSMUX_STAT_ERROR 0x08	#define HTSMUX_STAT_NORMAL 0x00 #define HTSMUX_STAT_BATT 0x01 #define HTSMUX_STAT_BUSY 0x02 #define HTSMUX_STAT_HALT 0x04 #define HTSMUX_STAT_ERROR 0x08
byte HTSMUXreadStatus(tSensors smux) {	byte HTSMUXreadStatus(byte smux) {
<pre>ubyte sendMsg[3]; ubyte readMsg[1]; sendMsg[0] = 2;</pre>	<pre>byte sendMsg[2]; byte readMsg[1]; int status = 0; const byte count = 1; sendMsg[0] = 0x10; // Address of SMUX sendMsg[1] = 0x21; // Status register // Send the command to the SMUX if(I2CBytes(smux, sendMsg, count, readMsg)) return readMsg[0]; else return -1; }</pre>
<pre>task main () { byte status = 0; SetSensorType(S1, sensorLowSpeed); wait1Msec (100); while (true) { eraseDisplay(); status = HTSMUXreadStatus(S1); nxtDisplayTextLine(1, "Status: %d",</pre>	<pre>task main () { byte status = 0; SetSensorLowspeed(IN_1); Wait(100); while (true) { ClearScreen(); status = HTSMUXreadStatus(IN_1); TextOut(0, LCD_LINE1, "Status: "); NumOut(45, LCD_LINE1, status); if(status & HTSMUX_STAT_BATT == HTSMUX_STAT_BATT) TextOut(0, LCD_LINE3, "No battery"); Wait(100); }</pre>

The status register function is so simple that I've included into a program directly as it does not need any helper functions. Play with it a bit, disconnect the battery pack and see what happens.

3rd Party ROBOTC Driver Suite

Some of the functionality in this document is part of the 3rd Party ROBOTC Driver Suite. The examples given in this document do not have any error checking or error recovery built into them, which the suite obviously does. The suite also handles access to the SMUX transparently, so you don't need to reassemble the I2C data bytes into a 16 or 32 bit value.

The website for this suite can be found here: http://rdpartyrobotcdr.sourceforge.net/, which also has a copy of the complete API documentation and source code for you to browse at your leisure.

I will be publishing an NXC port of my driver suite in the near future, so stay tuned.

Appendix A Register Layout + Function

Address	Туре	Contents		
00 – 07H	chars	Sensor version number		
08 – 0FH	chars	Manufacturer		
10 – 17H	chars	Sensor type		
18 – 1FH	bytes	Not used		
20H	byte	Command		
21H	byte	Status		
22H	byte	Channel 1 mode		
23H	byte	Channel 1 type		
24H	byte	Channel 1 I2C byte count		
25H	byte	Channel 1 I2C device address		
26H	byte	Channel 1 I2C memory address		
27H	byte	Channel 2 mode		
28H	byte	Channel 2 type		
29H	byte	Channel 2 I2C byte count		
2AH	byte	Channel 2 I2C device address		
2BH	byte	Channel 2 I2C memory address		
2CH	byte	Channel 3 mode		
2DH	byte	Channel 3 type		
2EH	byte	Channel 3 I2C byte count		
2FH	byte	Channel 3 I2C device address		
30H	byte	Channel 3 I2C memory address		
31H	byte	Channel 4 mode		
32H	byte	Channel 4 type		
33H	byte	Channel 4 I2C byte count		
34H	byte	Channel 4 I2C device address		
35H	byte	Channel 4 I2C memory address		
36H	byte	Channel 1 upper 8 bits		
37H	byte	Channel 1 lower 2 bits		
38H	byte	Channel 2 upper 8 bits		
39H	byte	Channel 2 lower 2 bits		
3AH	byte	Channel 3 upper 8 bits		
3BH	byte	Channel 3 lower 2 bits		
3CH	byte	Channel 4 upper 8 bits		
3DH	byte	Channel 4 lower 2 bits		
3E, 3FH	chars	Reserved		
40 – 4FH	bytes	Channel 1 I2C buffer		
50 – 5FH	bytes	Channel 2 I2C buffer		
60 – 6FH	bytes	Channel 3 I2C buffer		
70 – 7FH	bytes	Channel 4 I2C buffer		

Field	Function
Sensor version	Reports a revision number in the format "Vn.m" where n is the major version
	number and m is the revision level. Revision numbers typically reflect the
	firmware level. The version number is used to indicate the hardware level
Manufacturer	Contains "HiTechnc".
Sensor type	Contains "SensrMux".
Status	Used to monitor the operating state of the sensor multiplexer.
Channel 1/2/3/4 mode	Used to either read or set the operating mode for channels 1, 2, 3 or 4.
Channel 1/2/3/4 type	Used to read the sensor type for channels 1, 2, 3 or 4.
Channel 1/2/3/4 I2C	Used to specify the I2C read length for channels 1, 2, 3 or 4.
byte count	
Channel 1/2/3/4 I2C	Used to either read or set the I2C device address for channels 1, 2, 3 or 4.
device address	
Channel 1/2/3/4 I2C	Used to either read or set the I2C memory address for channels 1, 2, 3 or 4.
memory address	
Channel 1/2/3/4 upper	Hold the upper 8 bits of the most recent 10 bit value obtained from channels
8 bits	1, 2, 3 or 4 analog inputs.
The Channel 1/2/3/4	Hold the lower 2 bits of the most recent 10 bit value obtained from channels
lower 2 bits	1, 2, 3 or 4 analog inputs.
The Channel 1/2/3/4	Hold up to 16 bytes read from channels 1, 2, 3 or 4 I2C interfaces if those
I2C buffer	channels are set to I2C mode.

Appendix B: SMUX Status

The current status of the SMUX is reported in the 21H register as specified below.

D7	D6	D5	D4	D3	D2	D1	D1
-	-	-	-	Error	Halt	Busy	Batt

The status bits have the following meaning

Bit	Meaning if set		
Batt	No/low battery voltage detected		
Busy	Autodetect in progress		
Halt	SMUX halted		
Error	Command error detected		

Appendix C: Channel Mode

The channel mode registers (22H, 27H, 2CH and 31H) for each connected are as specified below.

D7	D6	D5	D4	D3	D2	D1	D1
-	-	-	Slow	Dig 1	Dig 0	9V en	I2C

The channel mode bits have the following meaning

Bit	Meaning if set		
I2C	The connected sensor is a digital sensor		
9v en	The analog pin is used as 9v supply pin		
Dig 0	The dig 0 pin is driven high		
Dig 1	The dig 1 pin is driven high		
Slow	The I2C read rate is decreased from 80Hz to 20Hz		

Appendix D: Channel Type

The channel type registers (23H, 28H, 2DH and 32H) contain the type of sensor that was detected during the autodetect phase. The registers can have the following values.

Туре	Sensor
0	Not an I2C sensor, also used for analogue sensors
1	LEGO ultrasonic sensor
2	HiTechnic compass sensor
3	HiTechnic color sensor
4	HiTechnic accelerometer sensor
5	HiTechnic IR seeker sensor
6	HiTechnic prototype board
7	HiTechnic new color sensor
8	Reserved
9	HiTechnic new IR seeker sensor

Appendix E: Supported sensors

Digital	Analogue
LEGO ultrasonic sensor	HiTechnic EOPD
HiTechnic compass sensor	HiTechnic Gyro
HiTechnic color sensor	LEGO Light Sensor
HiTechnic accelerometer sensor	LEGO Touch Sensor
HiTechnic IR seeker sensor	
HiTechnic prototype board	
HiTechnic new color sensor	
HiTechnic new IR seeker sensor	